

## **Molecular Conceptor 2 - Network Version - Quick Installation Card**

- Run '[DVDROM\_DRIVE]:\mc2\_setup.exe', this will start the setup menu application.

### **A. License Manager Server Installation.**

1. Insert the red NetHASP key into the computer.  
Press <ESC> to bypass the driver installation.
2. In the installation, choose **Custom Installation: Network Version** then check **License Manager** (optionally you can also check **Aladdin Monitor**)  
Follow the instructions.

For Windows 98 / ME: Select **Typical** setup type,

For Windows Server2008 / Vista / Server2003 / XP / 2000: Select **Service** setup type.

### **B. Molecular Conceptor Installation**

#### **Install on each client station or on a file server**

1. In the installation, choose **Custom Installation: Network Version** then check **Molecular Conceptor** and follow the instructions.
2. Edit 'nethasp.ini' (default location: c:\program files\synergix\mc2\nethasp.ini)  
  
Set the IP address of the License Manager Server.

### **C. Running Molecular Conceptor**

- For local installation, click –  
**Start Menu | Programs | Molecular Conceptor 2 | Molecular Conceptor 2 .**
- For file server installation, use a command line, you can optionally specify the user data directory for example:  
`%path\synergix\mc2\mc2.exe -pathuserdata "\\users\group A\john\\"`

**Teaching Package License:** By default, the quiz pages are disabled. If you want to enable your users to access the quiz pages, contact us at –  
[support@molecular-conceptor.com](mailto:support@molecular-conceptor.com)